

PatchCore ViT for Anomaly Detection

This document serves as a detailed guide to help users run the `patchcore_vit.py` script for anomaly detection. The script is designed to process datasets for training, validation, and testing, and generates anomaly heatmaps stored in a specified output directory.

Overview

The `patchcore_vit.py` script implements an anomaly detection model using PatchCore with a Vision Transformer (ViT) backbone. It allows users to specify dataset paths and output directories via command-line arguments (CLI).

Features

- Train an anomaly detection model with a specified training dataset.
 - Validate the model with normal and anomalous datasets to find the threshold.
 - Test the model and generate anomaly heatmaps.
 - Save the heatmaps to a user-specified directory.
-

Prerequisites

1. Environment Setup

Ensure you have Python installed (preferably Python 3.8 or higher). Install the required dependencies by running:

```
pip install -r requirements.txt
```

2. Directory Structure

Prepare your dataset directory with the following structure:

```

/training/
  /normal/      # Training dataset with normal images
/validation/
  /normal/      # Validation dataset with normal images
  /zflowers/    # Validation dataset with anomalous image
s
/testing/
  /normal/      # Testing dataset with normal images
  /zflowers/    # Testing dataset with anomalous images

```

Running the Script

Step 1: Command-Line Arguments

The script uses command-line arguments to accept dataset paths and output directories. Below is a description of each argument:

Argument	Description
<code>--train_dir</code>	Path to the training dataset.
<code>--val_normal_dir</code>	Path to the normal validation dataset.
<code>--val_anomalous_dir</code>	Path to the anomalous validation dataset.
<code>--test_normal_dir</code>	Path to the normal testing dataset.
<code>--test_anomalous_dir</code>	Path to the anomalous testing dataset.
<code>--output_dir</code>	Path to the output directory where anomaly heatmaps will be saved.
<code>--batch_size</code>	(Optional) Batch size for data loaders. Default is 4.

Step 2: Example Usage

To run the script, use the following command:

```

python patchcore_vit.py \
  --train_dir "/path/to/training/normal" \

```

```
--val_normal_dir "/path/to/validation/normal" \  
--val_anomalous_dir "/path/to/validation/zflowers" \  
--test_normal_dir "/path/to/testing/normal" \  
--test_anomalous_dir "/path/to/testing/zflowers" \  
--output_dir "./output/anomaly_heatmaps" \  
--batch_size 4
```

Step 3: Output

- The script will train the model using the training dataset.
- It will validate the model and find the best threshold.
- During the testing phase, it will generate anomaly heatmaps for anomalous images and calculate metrics such as accuracy, confusion matrix, and AUROC.
- The heatmaps will be saved in the specified output directory (e.g., `./output/anomaly_heatmaps`).

Understanding the Outputs

Heatmaps

- Each heatmap highlights the areas in an image where anomalies are detected.
- Saved in the output directory with filenames like `anomaly_visual_0.png`, `anomaly_visual_1.png`, etc.

Logs

- The script prints the progress of training, validation, and testing phases in the terminal.
- Metrics such as accuracy, confusion matrix, and AUROC are displayed for performance evaluation.

Troubleshooting

1. **Missing Dependencies:**

If you encounter errors related to missing libraries, ensure you have installed all dependencies from

`requirements.txt`.

2. **Invalid Dataset Paths:**

Double-check the paths provided in the CLI arguments. Ensure they point to valid directories containing images.

3. **Output Directory Not Found:**

If the output directory does not exist, the script will create it automatically.

Additional Information

Supported Image Formats

- The script supports `.jpg`, `.jpeg`, and `.png` image formats.

Batch Size

- The batch size can be adjusted based on your system's memory capacity. A larger batch size may speed up training but requires more memory.
-